


Totally Integrated Automation Portal									
名称	数据类型	偏移量	默认值	从 HMI/OP C UA/Web API 可访问	从 HM I/O PC UA/Web API 可写	在 HMI 工程组态中可见	设定值	监控	注释
Edge[3]	Bool	10.3	false	True	True	True	False		
Edge[4]	Bool	10.4	false	True	True	True	False		
Edge[5]	Bool	10.5	false	True	True	True	False		
Edge[6]	Bool	10.6	false	True	True	True	False		
Edge[7]	Bool	10.7	false	True	True	True	False		
Edge[8]	Bool	11.0	false	True	True	True	False		
Edge[9]	Bool	11.1	false	True	True	True	False		
Edge[10]	Bool	11.2	false	True	True	True	False		
Edge[11]	Bool	11.3	false	True	True	True	False		
Edge[12]	Bool	11.4	false	True	True	True	False		
Edge[13]	Bool	11.5	false	True	True	True	False		
Edge[14]	Bool	11.6	false	True	True	True	False		
Edge[15]	Bool	11.7	false	True	True	True	False		
NumSec	Int	12.0	0	True	True	True	False		
AS_Sec	Int	14.0	0	True	True	True	False		
StartTemp	Bool	16.0	false	True	True	True	False		
Temp									
Constant									
网络 1 :									
									
网络 2 :									

Totally Integrated Automation Portal		
#OnSb #OnSb(R)		
网络 3 :		
#OffSb #OffSb(R)		
网络 4 :		
#StartTemp#Run #StartTemp#Run #Edge[2]P"Clock_1Hz"%M0.5 #Edge[0]Q #Edge[2]NOT 0IN0OUT1#AS_Sec INCInt #AS_SecIN/OUT ENENO		
网络 5 :		
#AS_Sec>Int10 #Fail #Err		
网络 6 :		
网络 6 :		
#StartTemp "Clock_1Hz"%M0.5 #Edge[1]P #NumSecIN/OUT #NumSecIN/OUT #NumSec>=Int60 1 1 0IN0OUT1#NumSec #RunMinIN/OUT INCUDInt ENENO		
网络 7 :		

Totally Integrated Automation Portal		
#StartTemp #Start		